

Audited Database Properties window - Before-After Data tab

The Before-After Data tab of the Audited Database Properties window allows you to select the tables for which you want to collect before and after data. You can collect before and after data for DML events generated by DELETE, INSERT, and UPDATE commands.

Collect before and after data when it is critical to capture the exact data change in a table column. When this feature is enabled, you can evaluate the before value and after value for each change in the Audit Events view. Enabling this feature can impact your Collection Server and Management Console performance.

If you want to collect before and after data, verify that you are auditing DML events on this database and that common language runtime (CLR) is enabled on the corresponding SQL Server instance.

i IDERA provides limited support for before-after data auditing of the publisher database in SQL Servers with replication. However, this scenario is supported only when the publisher database with transaction replication is set to replicate data ONLY. **If the target database uses SQL Server replication set to replicate more than data**, do not enable before-after auditing. Before and after data collection does not support SQL Server replication in that situation. For more information, see Microsoft Books Online for the version of SQL Server you are using.

i To successfully audit specific columns on a table, ensure the table name does not contain the following special characters: \ / : * ? "

Audited Database Properties

DML/SELECT Filters | **Before-After Data** | Sensitive Columns | Trusted Users | Privileged User Auditing

Tables audited for DML Before-After data:

Table Name	Maximum Rows	Columns
Common.Alerts	10	All Columns

Add...
Remove
Edit...

Note: If you do not select any columns, all columns will be audited by default. Auditing before-after data can result in a significant amount of data being collected. You should audit before-after data for tables only when it is necessary to have the before and after data for DML activity within the table.

CLR Status

CLR is enabled for WIN-

Enable Now

[Learn how to optimize performance with audit settings.](#)

OK Cancel

Available actions

Specify tables for before and after data collection

Use **Add** and **Remove** to specify the tables for which you want to collect before and after data.

Specify which columns to audit

Use **Edit** to specify which columns you want to audit. You can audit all columns or individual columns that do not contain BLOB data.

Select the maximum number of rows to collect

Use **Edit** to select the number of rows per transaction that you want to audit from this table. For example, if you select 100 rows, the SQL Compliance Manager Agent will capture the first 100 rows of each DML transaction, and collect all column updates for each captured row. By default, the first 10 rows per DML transaction are captured.

Enable Now

Allows you to enable CLR on the instance hosting this database.

CLR is required by .NET Framework to access details about DML events on the SQL Server database. For more information, see Microsoft Books Online.

Available fields

Table Name

Provides the name of the table you are auditing on this database.

Maximum Rows

Provides the maximum number of rows that the SQL Compliance Manager Agent will capture of each DML transaction.

Columns

Indicates the status of the columns associated with the audited tables. Typically, this field displays **All Columns** or lists the individual columns that are audited for before-and-after data.

If the audited table contains BLOB data and individual columns that are not selected, the status will display as **Not Configured**. SQL Compliance Manager does not support auditing BLOB data. To audit data changes on this table, click **Edit** and then choose the available columns that do not contain BLOB data.

Set up auditing before and after data

Auditing before and after data is an extension of DML event auditing at the table column level.

1. Ensure Database Modification (DML) activity is selected on the Audited Activities tab.
2. Ensure the appropriate tables are specified on the [DML/SELECT Filters](#) tab.
3. On the Before-After Data tab, click **Add** to choose which audited tables should also be audited at the column level for before and after data.
4. Choose the appropriate tables, and then click **OK**. By default, all columns are audited.
5. *If you want to audit specific columns*, select the table, and then click **Edit**.