

Adding servers

This section includes the following topics:

- [Pre-installation tasks](#)
- [Adding a new server](#)
- [Post-installation action items](#)

Pre-installation tasks

Precise installer displays a series of screens. Most of the screens require you to input details regarding your information systems. Before defining server installation options, compile a list of all required user inputs based on the information below.

Before you define servers and install the Listener agents, verify that you have completed the following:

- Install Precise framework
- Check that the servers fulfill the Precise requirements as described in the Minimum Requirements document.
- Create a Precise user for each UNIX server.
- Close the Services window in the Control Panel if you are installing on a Windows server.

Common pre-installation tasks on Windows

You must perform the following pre-installation tasks regardless of the Precise components you intend to install. To perform common pre-installation tasks on Windows:

- Verify that the port of the NetBios is opened, if you want to monitor an instance remotely and you have a firewall between the local and remote servers.
- Create a user that has at least the privileges described in the privileges table, if you work with MS SQL Server and you are not using the local system user when installing Precise.

Table 6-1 Privileges

Goal	Privilege
Local policies	Act as part of the operating system Bypass traverse checking Deny login locally Increase quotas Lock pages in memory Log in as a batch job Log in as a service Profile single process Profile system performance Replace process level token
File system	Full control over <precise_root> folder Read access to the following files: <ul style="list-style-type: none">• windir\system32\PERFCxxx.DAT• windir\system32\PERFHxxx.DAT Full access to the following local folder: C:\Program Files\Microsoft SQL Server\MSSQL\
Windows registry	Full access to the following entry: <ul style="list-style-type: none">• HKEY_LOCAL_MACHINE\Software\PreciseSoftware Solutions• HKEY_LOCAL_MACHINE\System\CurrentControlSet\Control\SecurePipeServers\winreg• HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services Read access to the following entry: HKEY_LOCAL_MACHINE\Software\Microsoft\Windows NT\CurrentVersion\Perflib
Services privileges	Using sc . exe from the Windows resource kit, grant the same permissions of PU for the Precise user on the services.
MS SQL	System Administrator


Common pre-installation tasks on UNIX

You must perform the following pre-installation tasks regardless of the Precise components you intend to install.

To perform common pre-installation tasks on UNIX:

1. Create a software owner account with the following characteristics:
 - Password, other than NULL
 - Authorization to use the cron facility (only required if you intend to install an Oracle Tier Collector on the respective server)
 - On Linux, read and write permissions to the /dev/null special file
 - On Linux, install ksh. Unless you have purchased the AT&T version of ksh, you must download pdksh, a korn shell clone in the public domain. If you have Red Hat, you can download the Intel version of pdksh from the Red Hat Web site. For other Linux distributions and platforms, search for "pdksh" at: <http://rpmfind.net/linux/rpm2html/search.php?query=pdksh>
 - The Precise user must have a . (dot) in his Path variable
2. Check and perform, if applicable, the following:
 - If you use an HP-UX server, verify that the operating system updates that are required for Java Runtime Environment 1.6 are installed on it. For information on available updates, go to: <http://docs.hp.com/en/HPUXJAVAPATCHES/index.html>.
 - Verify that the user limits are as specified in the list or higher (the user limit can be changed and configured using the ulimit command):
 - time (seconds) unlimited
 - file (blocks) unlimited
 - data (kbytes) unlimited
3. If you use Linux 64 bits OS, install the Linux OS update to add support for running 32-bits applications. This update is referred to as the x86-compat-libs patch. You can install this update or any superseding update.

Adding a new server

 To install a Precise Listener on a Windows server, you must access it using a local administrator account.


To add a new server:

1. When installing a Tier instance, next to the Server with the Tier instance textbox, click **Add**.
2. Enter the server name or IP address for the server where you want to install the Precise Listener.
3. Enter the server type (Windows or UNIX) where you want to install the Precise Listener. This information determines the installation tasks to be performed.
4. Click **Next**.

Windows

If you selected Windows as the server type, follow these steps:


1. Select "Automatic Installation".
2. Select either:
 - "Use current credentials"
 - "Change credentials"
3. If you selected "Change credentials", follow these steps:
 - a. Enter user name with administrator privileges.
 - b. Enter the password for the Windows user.
 - c. Enter the domain or machine name in or on which the user account was created.
 - d. Enter the installation folder for the Precise Listener. This folder is also used for any other Precise component that you install on that server. To browse for an installation folder, click the **browse (...)** button. The name of the installation folder cannot contain foreign language characters. It should use English characters only.
4. Click **Next**.

 If you experience difficulty adding a server with automatic mode, you might need to use the manual mode. For more information, see Adding a Windows server using manual mode on page 49.

UNIX

If you selected UNIX as the server type, follow these steps

1. Select "Automatic Installation".
2. Enter the UNIX Precise-user name (which you created before).
3. Enter the password for the UNIX user.
4. Enter the installation folder for the Precise Listener. This folder is also used for any other Precise component that you install on that server. To browse for an installation folder, click the **browse (...)** button. The name of the installation folder cannot contain foreign language characters. It should be in English only.
5. Click **Next**.

 If you experience difficulty adding a server with automatic mode, you might need to use the manual mode. For more information, see Adding a UNIX server using manual mode on page 49.

Preview screen

This screen displays a summary of all information.

Installation Progress

This screen displays the installation progress.

Post-installation action items

Perform any action items that are indicated on the action items screen. If you are using a UNIX server, you have the option to add Precise startup to your machine startup.

Successful installation

The installation was completed successfully.

[IDERA](#) | [Products](#) | [Purchase](#) | [Support](#) | [Community](#) | [Resources](#) | [About Us](#) | [Legal](#)