## **Adding or Editing Monitors**

To add a new Monitor do the following:

- Click the Add new Monitor link from the drop-down in Monitors page.
- Choose the type of counter MySQL, System, or Custom SQL.
- Type in the name of the group to which this monitor is being added.
- Enter the name of the counter being added.

For editing a monitor, click Edit Monitor icon beside the monitor in Monitors page.

### Formula:

A MySQL server parameter that is needed to compute the value of this counter.

Value: Defines a function that computes the value.

#### Example:

```
function()
{
    if(MONyog.MySQL.Custom.Available != 1)
        return "(n/a)";
    return MONyog.MYSQL.GlobalVariables.max_allowed_packet;
}
```

For a detailed description of values, see Monyog Object Model for more information.

DocText:Description of Monitor.

Advise Text: Advise text to the Monitor being added.

ADD NEW MONITOR	× Close	✓ Save
General Advanced Alerts		
Name*		
Number of threads that can be cached		
Monitor Group*		
Threads New		
Type of counter         ©         System         ©         Custom SQL           Select "MySQL" or "System" based on whether this Monitor or Dashboard chart displays MySQL or system-related information. Sele is based on a Custom SQL Object. Refer help for more details.	ct "Custom SQL" if t	his Monitor
Enabled?  Select "Yes" to have MONyog evaluate this Monitor and display the output on the Monitors page.		
Formula		
thread_cache_size		
Value* function() { if(MONyog.MySQLCustom.Available != 1) return "(r/a)"; if(ToInt(MONyog.MySQLGlobal/Variables.thread_cache_size) > 0)	4	
Description		
Each connection to the MySQL database server runs in its own thread. Thread creation is a time consuming instead of killing the thread each time a connection is closed, the server can keep the thread in its thread co use it for a new connection later	activity, so ache and	

In this customization form each field corresponds to a valid MOM property. Some fields take on valid JavaScript expressions while others take on text /HTML as values. The values entered in these fields are used to generate JS objects which are basically name-value pairs.

The General tab displays properties which are basically necessary to define a Monitor. Properties with asterisk(\*) are mandatory. To customize the behavior of the Monitor further, click the **Advanced** that displays all MOM properties.



## Add generic functions

Common functions required across multiple Monitors can be put into generic functions. The generic functions shipped with SQL DM for MySQL cannot be edited. Only the user added generic functions will be editable. For example, the function StorageUnits defined in generic functions takes a numeric value as a parameter and returns a string which is the value specified in terms of K(ilo), M(ega), B(ytes), etc. To add a generic function click the icon adjacent to the title.

MANAGE GENERIC FUNCTIONS $\odot$		× Close
CacheHitRatioInnodb	Name*	
CacheHitRatioMyISAM	CpuUsageInfo	
CacheHitRatioQuery	Function name; must be a valid JavaScript identifer	
CacheHitRatioThread	Parameters	
CachePercentUsed	oliker oNice oSystem oldle olowait oki oSi	
CheckForInnoDB	Comma-separated list of function parameters; each parameter must be a valid JavaScript identifi	er .
CheckForSystem		
GetCpulOPercentage	Body*	_
GetCpuKernalPercentage	ret = GetCpuPercentage(pUser, pNice, pSystem, pIdle, plowajt, pHi, pSi);	
GetCpuPercentage	if(ret == -1)	
GetCpuUsed	return 0; }	
GetCpuUserPercentage	ret = (100-ret).toFixed(1);	
GetServerUptime	return ret;	
GetWarnStatusFloat	Function body; a set of valid JavaScript statements.	4
GetWarnStatusInt		
InnoDBCachePercentOnDisk	Concert Concert	
InnoDBLogPercentOnDisk	Gancei	
Isinnodb		
IsKernalVersionLessThan2dot6		
IsReplicationSlave		
IsSlaveRunning		
KeyCachePercentOnDisk		
MemoryRequired		

## Enable/Disable notification for a particular Monitor.

SQL DM for MySQL allows user to disable notification for a monitor for a particular server. When notification is enabled for a monitor it generates alerts for all the servers whose values are alertable which may include servers that are not of interest for that monitor. Hence, receiving unwanted alerts is completely irritable. Now, you can avoid notification for a particular server or group of servers by using the below API. The API action is to disableNotification and enableNotification.

#### Example API:

To disable notifications for "Percentage of max allowed reached" monitor under "connection history" monitor group for the servers under the tag "Prod".

```
$ Curl "http://192.168.1.1:5555/?
_object=MONyogAPI&_action=disableNotification&_groupid=5&_counterid=10&_tag=Prod"
```

To enable notifications for "Percentage of max allowed reached" monitor under "connection history" monitor group for a particular server named "Staging-DB".

# \$ Curl "http://192.168.1.1:5555/?\_object=MONyogAPI&\_action=enableNotification&\_groupid=5&\_counterid=10&\_server=StagingDB"

You can check the Group ID and Counter ID of a monitor by hovering over the name of the monitor on the monitors page.

IDERA | Products | Purchase | Support | Community | Resources | About Us | Legal