Change credentials

When you register an instance, you define certain credentials, or if you have the auto-registration option enabled, IDERA SQL Inventory Manager registers your instances using the **SQL Inventory Manager service account** as the default connection credentials.

If you need to change these credentials for several instances, you can change them directly by clicking **Edit Credentials** on the **Managed Instances** section n or **SQL Licensing** section of the **Instances** view. Note that to have this option enabled, you must select those instances whose credentials you want to change.

Below you can see the tabs and sections where you can find Edit Credentials. Click the images to view full size.

DERALE?	na ave a secon								ana in a	IDERA -	· · · · · · · · · · · · · · · · · · ·								****		1.00	en a com
Aller a ser 🔜	SALA CARACTERIAN							84. B		Anna Anna I		**										
and a state of the second s	Reichenschriftener	Harr	ed •							- Second Contraction of the International Contractional Contraction of the International Contraction of th	Bishesche	lana 50Li	instang	÷								
					0.11											1.0						
- a -	the particular (a)									with the second s	1.1 ye			and the								
wr	I Game	1.14	n vie	6.9	10	$\mathbb{Z}^{2\times n} \to \mathbb{Z}$	14.47	Service C.	2012	1917.	1 million	2.74	184.1	11		12	10		122		- ž	1 C
	18	O LOW	A: -03)	1	85	3.2		P	- V84 - 1	was named												. 32
	A 11	1 444							2772.4		100000	¢	n	27	~	F	1.00	·	·		1	- 17 m
	A 11.000 0.0000 0.000								and a		at the second second	N. A. A.			11.47							 March
	10 million and press		-	-A					And the second	1044.00		and the second										- 24
	10			in the second	с. ғ	1.4			in the second	 Anterna contra 	A CONTRACTOR	a de la compañía de la		1.400				÷	10			
	10	- i i		140 C	· ·	1.00			Service.		11000000				- 6197						-	a 😤
	10	e Mile e		14.7	· .	.e.c.			100		To assess	5 ann			New?						-1	1.322
	1 Berlin and State			14.1	·	6-6-°			272,4			14444			10.11							127.0.41
	10			14.1	·				2724		The second second			1.46.85	1.00		-	-	. P			- North
		0.0	\$1.5327	14.1	·	-			200		15.00				and the second	÷ .			22	A. 1		- 32
	10	0.0	S. 1996	-44.5	·				Sec. 1		_				194 D							n
	10	0.0	A. 1996	14314		M 74-			27.70		The second	• 1	Pit and	· · · · ·	114 . LA	-	*		~	-	24 C	1 (Same
					1. A.	10.0									5.54	1.144.1						

IDERA SQL Inventory Manager opens the Edit Credentials window where you can change your:

- SQL Connection Credentials
- WMI Connection Credentials

SQL Connection Credentials

These credentials allow you to connect to SQL Server instances to collect availability, capacity, and configuration data. To change these credentials, follow these steps:

- Go to the SQL Connection Credentials section.
- Choose between the IDERA SQL Inventory Manager service account, Windows user account, or SQL Server login account. The last two options
 require that you provide the respective login and password.
- After you define your SQL Connection Credentials, you can click TEST CREDENTIALS to make sure IDERA SQL Inventory Manager can use these credentials to gather data.

Edit Credentials	×
Credentials	
SQL Connection Credentials Specify the account to be used to gather instance Account Type	information.
SQL Inventory Manager service account	•
Specify the account to be used to gather host con Account Type SQL Inventory Manager service account	nputer information.
• Pro Tip: Test the credentials to make sure SQL Inventory Manager can gather data for	Test credentials
instances and host computers.	

A Note

When you have the auto-registration option enabled, IDERA SQL Inventory Manager uses the SQL Inventory Manager service account as the default SQL connection credentials.

WMI Connection Credentials

These credentials allow you to connect to the computer that hosts the SQL Server instance in order to collect its performance and computer details. To change these credentials, follow these steps:

- Go to the WMI Connection Credentials section.
- You can choose between the IDERA SQL Inventory Manager service account or Windows user account. If you choose the latter, you need to provide a login and password.
- After you define your WMI Connection Credentials, you can click TEST CREDENTIALS to make sure IDERA SQL Inventory Manager can use these credentials to gather data from host computers.

dit Credentials	×
Credentials	
SQL Connection Credentials Specify the account to be used to gather instance information.	
Account Type	
SQL Inventory Manager service account	•
WMI Connection Credentials Specify the account to be used to gather host computer informati	on.
VMI Connection Credentials	on.
WMI Connection Credentials Specify the account to be used to gather host computer informati	on.

A Note

....

When you have the auto-registration option enabled, IDERA SQL Inventory Manager uses the SQL Inventory Manager service account as the default WMI connection credentials.

You can also change credentials by accessing the **Edit Instance Properties** window. Keep in mind that the **Edit Instance Properties** window allows you to change credentials only for a specific instance. If you want to change connection credentials for several instances at once, use the **Edit credentials** opti on explained in this section. For more information about editing instance properties, see How to edit instance properties.

IDERA SQL Inventory Manager lets you discover and visualize your SQL Server environment. Learn more > >

IDERA Website	Products	Purchase	Support	Community	About Us	Resources	Legal
---------------	----------	----------	---------	-----------	----------	-----------	-------