Configure Advanced Connection Settings

The Advanced Connection Settings window of the SQL Doctor allows you to input options for how you want to collect performance counters.

Access the Advanced Connection Settings window

You can access the Advanced Connection Settings window by clicking **Advanced Connection Settings** in the Add Server window or by selecting **Edit > General Settings** and clicking the corresponding link.

The options available in the Advanced Connection Setting windows are not available for cloud instances. The Advanced Connection Setting is not available when SQL Doctor recognizes instances running on a Linux operating system.

Select your advanced connection settings

You can configure SQL Doctor to use either SQL Server OLE Automation or Windows Management Instrumentation (WMI) for collecting performance metrics from the selected instance.

SQL Server Automation

To use SQL Server OLE automation, check the **Use OLE Automation for collecting performance counters** box and then click **OK**.

SQL Server OLE	Automation options:	
Use OLE Auto	mation for collecting performance counters	
Windows Manage	ement Instrumentation (V/MI) connection ontions:	
Maakina munuge		
viacoine name:		
Hadenine name.	1	
User name:		
User name: Password:		

Windows Management Instrumentation

To use WMI for collection, type the user name and password in the appropriate fields. The **A uthority** field is optional when setting your WMI namespace security. Then click **OK** to close the Advanced Connection Settings window.

Windows Management Instrumentation (WMI) is not available on a Linux operating system.

So For more information about WMI connection, see the following Microsoft tip at http://techn et.microsoft.com/en-us/library/ee692772.aspx#EEAA.

IDERA | Products | Purchase | Support | Community | Resources | About Us | Legal