

Installing backup/restore components in a clustered environment

For a fault-tolerant backup and restore infrastructure, you must install the SQL Safe Backup Service and SQL Safe Filter Service on the computers hosting your SQL Servers. Although you are using a clustered environment, **you should not configure these services as clustered resources**. Doing so would compromise their functionality in *active-active* clustering configurations. In the case of InstantRestore, you can perform the optional step of executing a one-time command to enable failover support for SQL Safe hydration operations. See the following topic to enable fault tolerance for IR hydration per SQL Server instance.

Install or upgrade the SQL Safe backup and restore components via the SQL Safe Management Console

1. Install the SQL Safe Management Console onto a computer using the FULL Installer. You can install on any computer, as long as it can access the servers to which you want to deploy the SQL Safe Management Console.
2. Launch the SQL Safe Management Console.
3. Register the clustered SQL Server instances on which you want to install or upgrade SQL Safe by right-clicking **SQL Server Instances**, and then selecting **Register SQL Server**.
4. Right-click the SQL Server instance in the Servers tree, and then select **Install SQL Safe Backup Agent**.
5. Follow the on-screen instructions and finish deploying the Backup Service components.
6. Once this process is complete, click the **SQL Safe Agents** tab. SQL Safe displays the active and inactive node names of the clustered SQL Server onto which you installed the SQL Safe Backup Agent.
7. Right-click the first of the remaining nodes, and then select **Install Backup Agent**. Repeat this step for each of the remaining nodes to install or upgrade the Backup Service components on the remaining nodes.
8. Verify that the **Management Server** column matches the correct management service. This setting is automatically set during your installation or upgrade.
9. **If want to use InstantRestore functionality**, right-click the first node, and then choose **Enable SQL Safe Instant Restore**. Repeat this step for each of the remaining nodes. Your SQL Safe Backup Services are now installed.

Enable fault tolerance for InstantRestore Hydration per SQL Server instance (Optional)

This process is necessary only if you want fault tolerance for databases still going through the hydration process of InstantRestore. Before you begin, make sure that your SQL Safe Backup service components are already installed.

1. Remotely log on to a node of the cluster.
2. Open a new Command Window.
3. For each clustered SQL Server instance hosted on that cluster server, run the following command:
`SQL SafeCmd Cluster FilterService sqlserver_name`
 Where `sqlserver_name` is the full SQL Server name of the clustered SQL Server.

This command creates a Generic Script Resource that controls failover for Hydration operations for that specific SQL Server. Note that this command is run only once per clustered SQL Server, not per node.

SQL **Safe** is a high-performance backup and recovery solution for your SQL Servers. [Learn more](#) > >

IDERA Website	Products	Purchase	Support	Community	About Us	Resources	Legal
--------------------------	-----------------	-----------------	----------------	------------------	---------------------	------------------	--------------